

H Series Mobile Software User Manual

1 Software Overview

As to the H series products, vendor develops 2 kind of software for iPhone and Android separately, the mainly functions:

- With H.264 decode, the video will more smoothly when viewing through the Wan.
- Monitor the video with audio
- Control the P/T manually;
- Take photos, and browse the photos
- Visit the camera with IP address, DDNS, etc.


2 iPhone

2.1 Software for iPhone

Step1: Go to the【App Store】, search “hi smarteye”, “Wansview” or “smarteye” (F1 and F2)



(Figure 1)



(Figure 2)

Step2: Download and install the software as F3 and F4




(Figure 3)



(Figure 4)

Step3: Input the password of your App Store and finish install (F5 and F6)



(Figure 5)



(Figure 6)


2.2 How to use the software

(Notice: pleasure make sure the mobile phone can connect with internet.)



Step1: Find the finished software 【Hi Smarteye】as F1. Open it you will get F2



(Figure 1)



(Figure 2)

Step2: Click  button, you will get F3.click  button, please input the **【Device Info】** and **【Account Info】** of the camera.

Take NCH530W for example:


【Device Name】: For example: test;

【Device IP】: IP address or DDNS of the camera;

【Device Port】: Http port of the camera;

【User】【Name】: User name and password of the camera;

Then **【Save】** .




(Figure 3)




(Figure 4)

Step3: After **【Save】** , you will find the camera under the **【Devices】** (F5). Double click the camera, the video will show as F6.



(Figure 5)



(Figure 6)

3 Android

3.1 Software for Android

Mode 1: With Play Store in the phone

Step1: If your phone have **【Play Store】**, go to the **【Play Store】** as F1, and search “hi smarteye”, you will get F2




(Figure 1)




(Figure 2)

Step2: You will get F3 .Double click the “Hi Smarteye “, go to F4, install it.



(Figure 3)



(Figure 4)

Mode 2: No play store in the phone

- 1) Find the software in the CD, copy to the phone and install it.
- 2) Go to www.wansview.com to download the software, copy

to the phone and install it.


3.2 How to use the software

(Notice : Pleasure make sure the mobile phone can connect with internet.)



Step1: Find the finished software (Hi Smarteye) as F1. Open it you will get F2



(Figure 1)



(Figure 2)

Step2: Click  button, you will get F3. Click  button, please input the **【Device Info】** and **【Account Info】** of the camera.


Take NCH530W for example:

【Favorite】: For example: test;

【Server】: IP address or DDNS of the camera;

【Port】: HTTP port of the camera;

【User Name】【Password】: Username and password of the camera; Then **【Save】** .




(Figure 3)



(Figure 4)

Step3: After **【Save】** , you will find the camera under the **【Devices List】** (F5). Double click the camera, the video will show as F6.




(Figure 5)





(Figure 6)

4 Notice

- This software only supports the H Series latest version: 1.5 and above version. Can check the version on the System→DeviceInformation →Software Version under the webpage.



- Users can adjust the Video and Audio details under the Second Stream.



- Software for Android only supports G.711 Audio Type NOW.
- Any updates please pay attention to our website:

<http://www.wansview.com>